

# Rotational Ground Motion Parameters Catalog

## Rotational Ground Motion Parameters Catalog – General Description

Ground Motion Parameters Catalog contains data from the [Seismic catalog](#) and [Rotational Ground Motion Catalog](#) through the event ID. That data format can be made using the application [Ground Motion Parameters Catalog builder user guide](#).

The catalog is a variable in the Matlab format file and it is kept in a file MAT. The structure is an array with named fields that can contain data of various types and sizes. In the file there is only one variable, the file name and variable name are optional. The format of the Rotational Ground Motion Parameters Catalog is prepared in the same manner as the Catalog of seismic events, Ground Motion Catalog, and Ground Motion Parameters Catalog.

The variable describing the catalog is a vector of structures, consisting of fields:

- **field** – name of field in the catalog (text value);
- **type** – type of field in the catalog and way of showing the field (numeric value);
- **val** – column array of values. For the text the column is an array type cell with text fields. For the remaining value, the column is a numeric column.
- **unit** – description of unit for individual data (text value).
- **description** – short description of the parameter (text value).
- **fieldType** – semantic meaning of the field. When some field values are similar/related then fieldType name is entered and for another case [] is entered.

The fundamental is a full catalogue i.e. the variable contains the definitions of all specified fields. When some field values are missing then for the numeric data NaN (not specified) is entered and for the text null [] is entered. In the fields describing the events ("EID", "Time", "Lat", "Long" and at least one of Magnitude), the place of measurement ("RID", "SID", "S\_name", "S\_Lat", "S\_Long", "S\_Elevation", "R\_time") and at least one of the fields of rotation values in all rows must be present.

Field	Type	Val	unit	description	FieldType	Comments	Data format
<b>EID</b>	3	data vector		Event ID		<b>required field from Seismic Catalog</b>	text
<b>Time</b>	5	data vector		Event origin time		<b>required field from Seismic Catalog</b> , Matlab serial numerical time	double
<b>Lat</b>	14,15,24,25	data vector	deg	Latitude		<b>required field from Seismic Catalog</b> deg – North positive	double
<b>Long</b>	14,15,24,25,34,35	data vector	deg	Longitude		<b>required field from Seismic Catalog</b> deg – East positive	double
<b>Depth</b>	11-13	data vector	km	Hypocenter depth measured from the ground level		Hypocenter depth counted downwards from surface (positive values below surface)	double
<b>Elevation</b>	13	data vector	km	Hypocenter elevation measured over the sea level		Hypocenter elevation counted upwards from sea level (positive values above sea level, negative values below sea level)	double
<b>Mw</b>	4	data vector		Moment magnitude	'Magnitude'	<b>required field from Seismic Catalog when any other Magnitude is unavailable</b>	double
<b>ML</b>	4	data vector		Local magnitude	'Magnitude'	<b>required field from Seismic Catalog when any other Magnitude is unavailable</b>	double
<b>RID</b>	3	data vector		Registration ID		<b>required field. ID must be linked to the name of the rotational signal</b>	text
<b>SID</b>	3	data vector		Station ID		<b>required field</b>	text
<b>S_name</b>	3	data vector		Station name		<b>required field</b>	text
<b>S_Lat</b>	24,25	data vector	deg	Station latitude		<b>required field</b>	double
<b>S_Long</b>	24,25,34,35	data vector	deg	Station longitude		<b>required field</b>	double
<b>S_Elevation</b>	10	data vector	m	Station elevation		<b>required field</b>	double
<b>Epicentral_dist</b>	22	data vector	km	'Epicentral distance between event and station'		<b>required field</b>	
<b>R_Time</b>	5	data vector	days	Registration occurrence time		<b>required field</b>	double
<b>PRV_E</b>	13	data vector	rad/s	Peak ground rotational velocity of E component	PRV	<b>required field</b>	double
<b>PRV_N</b>	13	data vector	rad/s	Peak ground rotational velocity of N component	PRV	<b>required field</b>	double

# EPOS Thematic Core Service Anthropogenic Hazards

<b>PRV_V</b>	13	data vector	rad/s	Peak vertical ground rotational velocity	PRV	<b>required field</b>	double
<b>PRV_H</b>	13	data vector	rad/s	Peak horizontal ground rotational velocity	PRV		double
<b>PRV</b>	13	data vector	rad/s	Total peak ground rotational velocity	PRV		double
<b>PGA_E</b>	13	data vector	m/s^2	Peak ground acceleration of E component	PGA		double
<b>PGA_N</b>	13	data vector	m/s^2	Peak ground acceleration of N component	PGA		double
<b>PGA</b>	13	data vector	m/s^2	Total peak ground acceleration	PGA		double
<b>PVA</b>	13	data vector	m/s^2	Peak vertical acceleration	PGA		double
<b>PHA</b>	13	data vector	m/s^2	Peak horizontal acceleration	PGA		double

**Table 1. The general parameters in catalog MAT format.**

**Except for the general parameters described in the table above, the Rotational Ground Motion Parameters Catalog can contain other parameters in accordance with the Seismic Catalog, the Ground Motion Catalog or the Ground Motion Parameters Catalog.**

## The Numbers of Data type:

1 – the real data without limits,

2 – the integer data,

3 – text value,

4 – the real number rounded to 0.1 (shown as 11),

5 – time in Matlab format serial time – the time display format; seconds with accuracy 1/10,

6 – the real data display in an engineering manner with one decimal place, e.g.: 3.5E6, (obsolete, recommended 2cd)

7 – the real data display in an engineering manner with two decimal place, (obsolete, recommended 2cd)

bc – (b and c are code digits) the real data display in fix-point manner with at minimum b places before decimal and c decimal place

e.g. For number 3.149.

10: „3”

11: „3.1”

12: „3.15”

20: „03”

23: „03.149”

1bc– the same manner as bc, but with place for a sign (space for sign „+”, sign - for sign „-”)

2cd– (c and d are code digits), the real data is displayed in an engineering manner, with place for a sign (space for sign „+”, sign ‘-’ for sign „-”), with c decimal place and exponent expressed by d places. The sign in exponent is always displayed.

e.g. For number 0.001:

211: „1.0E-3”

221: „1.00E-3”

212: „1.0E-03”

222: „1.00E-03”

e.g. For number 1000:

211: „1.0E+3”

221: „1.00E+3”

212: „1.0E+03”

222: „1.00E+03”

[Back to top](#)